# **DriverPower Documentation**

Release 1.0.0

**Shimin Shuai** 

## Documentation

| 1 | Installation guide |   |   |  |  |
|---|--------------------|---|---|--|--|
|   | 1.1                | Install from pypi                                   | 1 |  |  |
|   | 1.2                | Install from source                                 | 1 |  |  |
| 2 | Quic               | k start   | 3 |  |  |
|   | 2.1                | Step 0: Define the task                             | 3 |  |  |
|   | 2.2                | Step 1: Prepare the data                            | 3 |  |  |
|   | 2.3                | Step 2: Build the background mutation rate model    |   |  |  |
|   | 2.4                | Step 3: Call the driver candidates                  |   |  |  |
| 3 | Com                | mand-line interface                                 | 5 |  |  |
|   | 3.1                | The model sub-command                               | 5 |  |  |
|   | 3.2                | The infer sub-command                               |   |  |  |
| 4 | Data               |   | 9 |  |  |
|   | 4.1                | Response table (response)                           | 9 |  |  |
|   | 4.2                | Feature table (feature)                             | 9 |  |  |
|   | 4.3                | Feature importance table (featImp) 1                |   |  |  |
|   | 4.4                | Functional score table (funcScore) 1                | C |  |  |
|   | 4.5                | Model and model information files (output of model) | 1 |  |  |
|   | 4.6                | Result table (output of infer)                      |   |  |  |
| 5 | Licei              | nse 1   | 3 |  |  |

## CHAPTER 1

### Installation guide

DriverPower requires Python >= 3.5 and some other computing packages. If you don't have Python 3.5 or higher, we recommend to install Python with Anaconda.

### 1.1 Install from pypi

You can install DriverPower from the Python Package Index (PyPI) by simply typing the following command in your terminal:

```
$ pip install driverpower
```

**Important:** DriverPower requires XGBoost for building gradient boosting machines. pip may not install XGBoost correctly especially for OS X owing to C++ compiler issue. See XGBoost installation guides for more information.

#### 1.2 Install from source

You can also download the latest source from GitHub to install. For example, to install version 1.0.0:

```
$ tar -xzf DriverPower-1.0.0.tar.gz
$ cd DriverPower-1.0.0/ && pip install .
```


See the importance note above if you have issue with the XGBoost installation.

Quick start

### 2.1 Step 0: Define the task

DriverPower aims to identify cancer driver candidates from **somatic** variants of a tumour cohort. The minimal number of samples required in the PCAWG study is 15. However, more samples will have more power to detect rare driver events. Both whole-genome sequencing and panel sequencing variants can be used.

The basic test unit accepted by DriverPower is called a **genomic element**, which is a set of disjoint (or continuous) genomic regions (see the figure below). In our manuscript, we also removed all blacklist regions to reduce the effect of variant artifacts. In the real world, a genomic element can be all exons of a gene, or all TF binding sites among a promoter etc.



Typically 1K to 100K genomic elements are tested together such as ~20K genes in the human genome. For each element, given its functional impact, mutational burden as well as thousands of features, DriverPower will report a p-value and q-value associated with that element.

### 2.2 Step 1: Prepare the data

DriverPower runs on processed training and test data as described in *data format*.

### 2.3 Step 2: Build the background mutation rate model

The background mutation rate (BMR) model is used to estimate the expected number of somatic mutations for each genomic element, given its features. DriverPower sub-command model is used to train BMR models. To build the BMR model, training features (X) and responses (y) are required. DriverPower supports two algorithms for the BMR model, generalized linear models (GLM) and gradient boosting machines (GBM).

See the model sub-command for all parameters and notes. Example code snippets are as follows:

Listing 2.1: Train a generalized linear model with feature selection by randomized lasso

```
$ driverpower model \
   --feature PATH_TO_X \
   --response PATH_TO_y \
   --method GLM
```

Listing 2.2: Train a gradient boosting machine with default parameters

```
$ driverpower model \
    --feature PATH_TO_X \
    --response PATH_TO_y \
    --method GBM
```

### 2.4 Step 3: Call the driver candidates

Listing 2.3: Call driver candidates with CADD scores

```
$ driverpower infer \
    --feature PATH_TO_X \
    --response PATH_TO_y \
    --modelInfo PATH_TO_model_info \
    --funcScore PATH_TO_func_score \
    --funcScoreCut 'CADD:0.01' \
    --name 'DriverPower' \
    --outDir ./output/
```

## CHAPTER 3

### Command-line interface

DriverPower uses a command-line interface. To view available sub-commands and usage of DriverPower, type

```
$ driverpower -h
usage: driverpower [-h] [-v] {model,infer} ...

DriverPower v1.0.0: Combined burden and functional impact tests for coding and non-coding cancer driver discovery

optional arguments:
   -h, --help show this help message and exit
   -v, --version Print the version of DriverPower

The DriverPower sub-commands include:
   {model,infer}
   model Build the background mutation model
   infer Infer driver elements
```

#### 3.1 The model sub-command

The model sub-command is used to build the background mutation model with training data. Command-line options for this command can be viewed as follows:

```
--feature str
--response str
                       Path to the training feature table (default: None)
                       Path to the training response table (default: None)
  --featImp str
                       Path to the feature importance table [optional]
                        (default: None)
parameters:
  --method {GLM, GBM} Algorithms to use (default: None)
  --featImpCut float Cutoff of feature importance score [optional] (default:
                       0.5)
  --gbmParam str Path to the parameter pickle [optional] (default: None) --gbmFold int Train gbm with k-fold, k>=2 [optional] (default: 3)
                       Identifier for output files [optional] (default:
  --name str
                        DriverPower)
  --modelDir str
                        Directory of output model files [optional] (default:
                        ./output/)
```

#### • Input

- Required data: --feature and --response for training elements.
- Optional data: --featImp.

#### Output

- all output files are in --modelDir.
- [name].GLM.model.pkl: the GLM model file.
- [name].GBM.model.fold[k]: the GBM model files.
- [name].[GLM|GBM].model\_info.pkl: the corresponding GLM or GBM model information.
- [name] .feature\_importance.tsv: the feature importance table, which is returned when no input --featImp. For GLM, feature importance is the number of times a feature is used by randomized lasso. For GBM, feature importance is the average gain of the feature across all gradient boosting trees.

**Important:** Please **DO NOT** rename the model files because their names are recorded in model information. Model files can be moved to another directory as long as --modelDir is specified in infer.

#### Parameters

- --method: [required] method used for the background model. Must be GLM or GBM.
- --featImpCut: [optional] cutoff for feature importance score. Features with score >= cutoff will be used in the model. Only used for GLM. Default is 0.5.
- -- gbmParam: [optional] path to the parameter pickle for GBM. The pickle file must contain a valid python dictionary for XGBoost parameters.
- --gbmFold: [optional] Number of model fold to train for GBM. Fold must be an integer >= 2. Default value is 3.
- -- name: [optional] Prefix for output files. Default is 'DriverPower'.
- --modelDir: [optional] Directory for output model and model information files. Default is './output'.

#### Notes

- Input data requirements can be found at *data format*.
- --gbmFold controls the split of training data by k-fold cross-validation. For example, default 3-fold model means the training data are divided into 3 equal folds. Each time, two folds of data are used to train

the model and the rest fold is used to validate the model. Hence, three model files will be generated at the end. The prediction will then be the average of three models.

- Training phase can take hours for large training set and consume a large amount of memories. For example, using our default training set (~1M elements and 1373 features), training randomized lasso plus GLM with single core takes about 2-10 hours and 80G RAMs. Training 3-fold GBM with 15 cores takes about 10-24 hours and 80G RAMs.
- The default pickle file for --gbmParam is generated as follow:

```
import pickle
# Default parameter for XGBoost used in DriverPower
param = {'max_depth': 8,
         'eta': 0.05, # learning rate
         'subsample': 0.6,
         'nthread': 15, # number of threads; recommend using the number of available,
- CPUs
         'objective': 'count:poisson',
         'max_delta_step': 1.2,
         'eval_metric': 'poisson-nloglik',
         'silent': 1,
         'verbose_eval': 100, # print evaluation every 100 rounds
         'early_stopping_rounds': 5,
         'num_boost_round': 5000 # max number of rounds; usually stop within 1500,
→ rounds
# Dump to pickle
with open('xgb_param.pkl', 'wb') as f:
   pickle.dump(param, f)
```

### 3.2 The infer sub-command

The infer sub-command is used to call drivers from test data with pre-trained models. Command-line options for this command can be viewed as follows:

```
$ driverpower infer -h
usage: driverpower infer [-h] --feature str --response str --modelInfo str
                         [--funcScore str]
                         [--method {auto, binomial, negative_binomial}]
                         [--scale float] [--funcScoreCut str] [--geoMean bool]
                         [--modelDir str] [--name str] [--outDir str]
optional arguments:
 -h, --help
                        show this help message and exit
input data:
 --feature str
                       Path to the test feature table (default: None)
 --response str
                      Path to the test response table (default: None)
 --modelInfo str
                      Path to the model information (default: None)
 --funcScore str
                      Path to the functional score table [optional]
                       (default: None)
parameters:
 --method {auto, binomial, negative_binomial}
```

```
Test method to use [optional] (default: auto)
                      Scaling factor for theta in negative binomial
--scale float
                     distribution [optional] (default: 1)
                     Score name: cutoff pairs for all scores
--funcScoreCut str
                     e.g., "CADD: 0.01; DANN: 0.03; EIGEN: 0.3" [optional]
                      (default: None)
--geoMean bool
                     Use geometric mean in test [optional] (default: True)
                     Directory of the trained model(s) [optional] (default:
--modelDir str
                      None)
                     Identifier for output files [optional] (default:
--name str
                      DriverPower)
--outDir str
                      Directory of output files [optional] (default:
                      ./output/)
```

#### • Input

- Required data: --feature and --response for test elements; --modelInfo from driverpower model.
- Optional data: --funcScore. Only required for test with functional adjustment.

#### Output

- Driver discovery result saved in "[outDir]/[name].result.tsv".

#### Parameters

- --method: [optional] probability distribution used to generate p-values (binomial, negative\_binomial or auto). Default is auto, which means decision will be made automatically based on the dispersion test of training data.
- --scale: [optional] scaling factor of theta for negative binomial distribution. The theta is calculated from dispersion test. Default is 1. Only used for negative binomial distribution.
- --funcScoreCut: [optional] Cutoff of each functional impact scores. The format of this parameter is a string in "NAME1:CUTOFF1;NAME2:CUTOFF2...", such as "CADD:0.01;DANN:0.03;EIGEN:0.3".
   Cutoff must in (0,1] and the name must match column names of --funcScore.
- --geoMean: [optional] Whether to use geometric mean of nMut and nSample in test. Default is True.
- --modelDir: [optional] Directory of model files from driverpower model. Only required when models have been moved to a different directory.
- -- name: [optional] Prefix for output files. Default is 'DriverPower'.
- --outDir: [optional] Directory for output files. Default is './output/'.

#### Notes

## CHAPTER 4

Data format

### 4.1 Response table (--response)

The response (y; dependent variable) table records the observed number of mutations, number of mutated samples and the length per genomic element. This table is required for both model (training) and infer (test) sub-commands.

1. Format: TSV (tab-delimited text) with header. Compressed tables are also accepted.

#### 2. Fields:

- binID: identifier of genomic element and used as key.
- length: effective length of the element.
- nMut: number of observed mutations.
- nSample: number of observed samples with mutations.
- N: total number of samples.

#### 3. Example:

| binID    | length | nMut | nSample | N |
|----------|--------|------|---------|---|
| TP53.CDS |        |      |         |   |
| KRAS.CDS |        |      |         |   |
|          |        |      |         |   |

### 4.2 Feature table (--feature)

The feature (X; independent variable) table records genomic features per element. This table can be large ( $\sim$ 10GB) for thousands of features and  $\sim$ 1M genomic elements. This table is required for both model (training) and infer (test) sub-commands.

#### 1. Format:

• TSV (or compressed TSV) with header. Loading may be slow for large datasets.

• HDF5 (\*.h5 or \*.hdf5). The HDF5 must contain key X, which is the feature table in pandas.DataFrame. Used for fast loading.

#### 2. Fields:

- binID: identifier of genomic element and used as key.
- Column 2+: one feature per column. Unique feature names are required.

#### 3. Example:

| binID    | GERP    | E128-H3K27ac |  |
|----------|---------|--------------|--|
| TP53.CDS | 4.80287 | 1.19475      |  |
| KRAS.CDS | 3.56563 | 2.53435      |  |

### 4.3 Feature importance table (--featImp)

The feature importance table records the feature importance score derived from randomized lasso, gradient boosting machine or other algorithms. This table can be used together with the <code>--featCut</code> argument to specify features kept in the background model. This table is only used and optional for the <code>model</code> sub-command with method <code>GLM</code>. If not provided, DriverPower will generate and output it automatically.

1. Format: TSV (or compressed TSV) with header.

#### 2. Fields:

- name: name of features, should match the column name in feature table.
- importance: feature importance score.

#### 3. Example:

| name         | importance |
|--------------|------------|
| GERP         | 0.3        |
| E128-H3K27ac | 0.5        |
| •••          |            |

### 4.4 Functional score table (--funcScore)

The functional score table records the functional impact score per genomic element. DriverPower can work with any functional impact score scheme. This table is only used and optional for the infer sub-command.

1. Format: TSV (compressed TSV) with header.

#### 2. Fields:

- binID: identifier of genomic element and used as key.
- Column 2+: one type of functional impact score per column.

#### 3. Example:

| binID    | CADD    | EIGEN   |  |
|----------|---------|---------|--|
| TP53.CDS | 4.80287 | 1.19475 |  |
| KRAS.CDS | 3.56563 | 2.53435 |  |

- 4.5 Model and model information files (output of model)
- 4.6 Result table (output of infer)

|          |                  |            |    |        | Г |
|----------|------------------|------------|----|--------|---|
| $\sim$ L | $\perp$ $\wedge$ | ם.         | ΓF | $\Box$ |   |
| ι, г     | $\neg$           | \ <b>—</b> |    | П.     |   |

License

DriverPower is distributed under the terms of the GNU General Public License v3.0